

# Table of Contents

- Create Site types** ..... 1
- Step 1** ..... 1
- Step 2a - Global site type configuration** ..... 1
- Step 2b - Uploading an image** ..... 1
- Step 3 - Service classes within the client** ..... 1
- Step 4 - Service class configuration** ..... 2
- Step 5 - Linking the service class to the image.** ..... 2




# Create Site types

In the following article we will create a site type for a datacenter. This datacenter is constructed as a three tier redundant architecture as described in the [Cisco Data Center Infrastructure 2.5 Design Guide](#) In this architecture we will have the following components:

- 1 redundant core
- 0:n redundant aggregation switches, with a maximum of 10 aggregation layers
- 0:n redundant access switches, with no maximum.

The architecture is represented in the image below. 

## Step 1


Open the [Site types](#) tab in the modeling form. Then click **+**. Choose the Client type and type the Site type. When the input is correct, click .

## Step 2a - Global site type configuration


The next step is configuring the Site type. There are 6 parameters to be set:

- (optional) The site type number.
- (optional) The site class.
- Max sites/Client\_type.
- Max sites/Client.
- Name format.
- Caption.

## Step 2b - Uploading an image

It is possible to upload an image representing the architecture. This is done by clicking  and selecting the image. [JPEG](#), [GIF](#) and [PNG](#) images can be used.

## Step 3 - Service classes within the client

Adding the service classes. Because we have a 3 tier architecture, 3 service classes will be created. Click **+**, type the name of the service class and click .

The Service class name will be unique for the Client type, NOT the Site type. So when choosing the service class name, be sure to choose a name for the function in the entire Client type.

In this example the service classes *DC\_CORE*, *DC\_AGGREGATE* and *DC\_ACCESS* will be created.

## Step 4 - Service class configuration

After the creation of the service classes, each service class must be configured. First select the *DC\_CORE* service class. The Max Services/Site value must be set to 1 (default). The Hierarchy ID will be set to 110 and the Description will be set to CORE.

Second select the *DC\_AGGREGATE* service class. The Max Services/Site value must be set to 10. The Hierarchy ID will be set to 111 and the Description will be set to AGGREGATE.

Last select the *DC\_ACCESS* service class. The Max Services/Site value must be set to 0 (no limit). The Hierarchy ID will be set to 112 and the Description will be set to ACCESS.

## Step 5 - Linking the service class to the image.

It is possible to link a service class to a position on the image. That way a service class can be added by clicking on the image.

Select the service class and then lasso around the target area.



Both the CORE and the AGGREGATION will be linked. Because the ACCESS layer must be linked to an aggregation layer, the ACCESS layer will be added from the service class details of the target aggregation layer. Therefore the ACCESS layer will not be linked on the image.

From:  
<http://wiki.netyce.com/> - Knowledge base

Permanent link:  
<http://wiki.netyce.com/doku.php/guides:user:sitetypes>

Last update: **2019/12/23 09:33**

