

# Template usage

Use the template usage tool to find out which node(s) are using a main-, sub- or port template: you can also filter on the desired client type.

## Filter on client type

The “Select” drop-down menus of this tool allow you to find those nodes using the selected main-template, sub-template or port-template. By default these menus show you all relevant templates of that type.

To limit the number of menu items, the “Filter” box beside the menu can be used. By entering a substring of the desired template name(s), the menu will refresh itself and show only those entries with the matching substring.

Normally the operator will first select the Client-type to narrow the set of main/sub/port templates to that client-type. Then, by selecting the appropriate template type(s), the nodes that depend on those templates are filtered.

It is possible to apply a Main-template and a Sub-template selection, or a Main-template and a Port-template selection at the same time, but not a Sub-template and Port-template simultaneously.

The resulting set of nodes can be used for reporting purposes, but is more commonly used to create a set of Command-jobs to push an updated Sub-template to the nodes using it. When doing so, please be aware that if the Sub-template is included using a conditional, the Command-job the operator creates should likewise include the conditional. Otherwise the Sub-template might be configured on a device that will normally not include it.



## Filter on client type and main template



## Filter on client type and sub template

| Network / Client | Select | Filter |
|------------------|--------|--------|
| Client type      | A      |        |

  

| Template type | Select    | Filter |
|---------------|-----------|--------|
| Main          | -- any -- |        |
| Sub           | UCL_base  |        |
| Port          | -- any -- |        |

**Find nodes**

Tracing nodes for template '**UCL\_base**'

Sub-template of 27 nodes

- A-003-002
- A-003-003
- A-003-004
- A-003-005
- A-003-006
- A-003-007
- A-003-008
- A-003-009
- A-003-010
- A-004-002
- A-004-003
- A-004-004
- A-004-005
- A-004-006
- UC02-002
- UC02-003
- UC02-004
- UC02-005
- UC02-006
- UC02-007
- UC02-008
- UC02-009
- UC02-010
- UC02-011
- UC02-012
- UC02-013
- UC02-014

### Filter on client type and port template



From: <https://wiki.netyce.com/> - **Technical documentation**

Permanent link: [https://wiki.netyce.com/doku.php?id=menu:build:templates:tpl\\_usage](https://wiki.netyce.com/doku.php?id=menu:build:templates:tpl_usage)

Last update: **2024/07/03 12:31**

