2025/12/04 23:10 1/1 FAQ topics

FAQ topics

Q I'm logged in the GUI but can't see the grids.

A You are trying to use the FQDN while the application is set to using the IP address or the other way around. Run yce_setup.pl and set DNS resolved to either yes/no, depending on your environment.

Q After logging in nothing is shown at all.

A Make sure you are allowed to access the NetYCE system using either TCP port 80/443 and port 8080. See: YCE Connection matrix

Q Where do I find the latest patches and licenses?

A Patches and licenses

Q Can't access the GUI, showing {{ version }}

A Make sure you've run 'net setup.pl' as root, 'yce_setup.pl' as 'yce'-user.

- 1. verify all processes are running using 'go ps'
- 2. if mysql is not running, execute: mysql_repair.sh as 'yce'-user
- 3. execute 'go up' for the remaining processes
- 4. Make sure all necessary ports are reachable, connection matrix

| \$ go ps | | | | | | | |
|----------|------|------|-------|------|----------|-------------|---|
| UID | PID | PPID | %MEM | %CPU | START | FNAME | CMD |
| root | 1451 | 1 | 3.25 | 0.01 | 10:05:48 | yce_psmon | opt/yce/bin/yce_psmondaemon |
| yce | 2863 | 2861 | 0.18 | 0.11 | 10:45:39 | sshd | sshd: yce@pts/0 |
| yce | 2864 | 2863 | 0.24 | 0.16 | 10:45:39 | bash | -bash |
| root | 2180 | 1 | 0.37 | 0.01 | 10:05:49 | httpd | /usr/sbin/httpd |
| yce | 2184 | 2180 | 0.24 | 0.00 | 10:05:49 | httpd | /usr/sbin/httpd |
| yce | 2185 | 2180 | 0.24 | 0.00 | 10:05:49 | httpd | /usr/sbin/httpd |
| yce | 2186 | 2180 | 0.24 | 0.00 | 10:05:49 | httpd | /usr/sbin/httpd |
| yce | 2187 | 2180 | 0.25 | 0.00 | 10:05:49 | httpd | /usr/sbin/httpd |
| root | 2219 | 1 | 0.08 | 0.00 | 10:05:50 | vsftpd | /usr/sbin/vsftpd /etc/vsftpd/vsftpd.conf |
| yce | 2312 | 1 | 2.41 | 0.00 | 10:05:50 | yce_tftpd | /opt/yce/bin/yce_tftpd |
| yce | 2338 | 1 | 3.10 | 0.06 | 10:05:50 | yce_sched | /opt/yce/bin/yce_sched |
| yce | 2354 | 1 | 5.80 | 0.08 | 10:05:51 | mojo | /opt/yce/mojo/yce.pl |
| yce | 2355 | 2354 | 5.58 | 0.01 | 10:05:51 | mojo | /opt/yce/mojo/yce.pl |
| yce | 2356 | 2354 | 5.58 | 0.01 | 10:05:51 | mojo | /opt/yce/mojo/yce.pl |
| yce | 2357 | 2354 | 5.58 | 0.00 | 10:05:51 | mojo | /opt/yce/mojo/yce.pl |
| yce | 2358 | 2354 | 5.58 | 0.01 | 10:05:51 | mojo | /opt/yce/mojo/yce.pl |
| yce | 2359 | 2354 | 5.58 | 0.01 | 10:05:51 | mojo | /opt/yce/mojo/yce.pl |
| yce | 2360 | 2354 | 5.58 | 0.01 | 10:05:51 | mojo | /opt/yce/mojo/yce.pl |
| yce | 2384 | 1 | 2.96 | 0.00 | 10:05:52 | yce_xch | /opt/yce/bin/yce_xch |
| root | 4297 | 1 | 0.14 | 0.01 | 10:47:44 | mysqld_safe | /bin/sh /usr/bin/mysqld_safedatadir=/var, |
| yce | 4494 | 4297 | 10.05 | 0.16 | 10:47:44 | mysqld | /usr/sbin/mysqldbasedir=/usrdatadir=/v |
| yce | 5236 | 1 | 4.59 | 0.53 | 10:48:03 | yce_skulker | /opt/yce/bin/yce_skulker |
| yce | 5322 | 1 | 4.41 | 0.00 | 10:48:07 | yce_nccmd | /opt/yce/bin/yce_nccmd |

From:

https://wiki.netyce.com/ - Technical documentation

Permanent link:

https://wiki.netyce.com/doku.php?id=guides:faq:faq_topics

Last update: 2024/07/03 12:31

